

MATERIAL AND SOFTWARE CONFIGURATIONS REQUIRED - MS SQL

[Printable Version](#)

OBJECTIVE

This page groups different components or configurations recommended to run the SQL server with the **maestro*** SQL database optimally.

SUMMARY

- [Internet and Network Access](#)
- [Operating System](#)
- [SQL Server Edition](#)
- [.NET Framework](#)
- [Hard Drive](#)
- [Memory](#)
- [Processors](#)
- [Monitor](#)
- [Antivirus](#)
- [Additional Information](#)

Internet and Network Access

- Internet access is required to authenticate SQL Server licenses and updates;
- A wired Ethernet network is required:
 - 100 Mb/s minimum;
 - 1 Gb/s or more recommended.
- Wireless connections (WiFi) are not supported.
- TCP / IP IPv4 must be enabled.
 - TCP / IPv6 is not supported.
- Port 1433 must be configured to pass through the Windows Firewall.

Operating System

The supported operating system is *Windows Server 2012 R2* or higher.

SQL Server Edition

The standard (or superior) edition is required.

.NET Framework

The *.NET Framework 4.8* is required for the database engine support.

Hard Drive

A minimum of two hard disk of 500 Gb of available space is required. The hard drive must be configured in NTFS file system. FAT32 is not supported.

Memory

A minimum of 24 Gb of memory is required.

Processors

A minimum of 4 2.2 GHz cores is required.

SQL Server installation is supported only on x64 processors. It is no longer supported on x86 processors.

Monitor

A monitor with 1280 x 720 resolution with 16-bit color.



Starting with version 3.05, the minimum resolution required is **1366 x 768**.

Antivirus

The data directory must be excluded from the antivirus scan.

Some antiviruses also require the exclusion of the software installation directory.

Additional Information

We recommend running *SQL Server* on computers with a NTFS or ReFS file format.

Running *SQL Server* on a virtual machine is slower than running in native mode because of virtualization overhead.

Last modification: July 07, 2025